



Razorcat Development GmbH
Witzlebenplatz 4
14057 Berlin
Germany

Technical Support

phone +49 - (30) - 536 357 0
fax +49 - (30) - 536 357 60
email support@razorcat.com
www <http://www.razorcat.com>

Release Notes

Release v4.2.23 (26 items)

C++

TES-4710

If an advanced stub parameter or return is a class with a base class an erroneous class was created.

C++

TES-5396

Fixed "Testobject 'function_name' not found" error if the test object is used as an extern "C" friend function of a class.

CTE

TES-4630

Fixed omitted test data for array elements in complex union structures.

Compiler/Target/Microcontroller

Enhancement

TES-4820

Adjusted the Slave Call for the TASKING Script debugger.

Compiler/Target/Microcontroller

TES-5312

Fixed MinGW error regarding `__attribute__((packed))`.

Compiler/Target/Microcontroller

Enhancement

TES-5400

Added Renesas GDB-Skript for RX140.

Compiler/Target/Microcontroller

TES-5402

Fixed deleting temporary files using TRACE32 as debugger.

Component Test

TES-4982

Fixed empty array data entries in report for time steps without test data but with eval macros.

Release v4.2.23 (26 items)

Coverage Viewer (CV)

TES-4813

Number of unreached/reached decisions within the ASCII coverage report was incorrect for test objects containing switch statements with conditions in the selector (The total coverage percentage was calculated correctly).

Coverage Viewer (CV)

TES-4814

Source in Coverage Viewer was not always colored correctly when a test object was not in the first source of a modules sources.

Defines

TES-4632

32 bit define Values with suffix 'L' were calculated with 16 bit width for 16 bit compilers.

Driver

TES-4582

Fixed generating code for a static @far function returning pointer to @far memory. (Cosmic Compiler)

Driver

TES-4604

Fixed generated code to get / set targets of advanced stub pointers.

Driver

TES-5139

Reduced high consumption of memory by interface database in test driver generator.

Enhancement

Import/Export

TES-4605

Set passing direction of advanced stub pointers to the passing direction of the target when importing test data.

Instrumenter

TES-4412

C1 total coverage was calculated incorrect if the return statement is a ternary conditional operator.

Instrumenter

TES-4586

Fixed erroneous calculation of total branches for branch (C1) coverage in case of mixed arithmetic and logical expressions (which will not be instrumented for coverage measurement, e.g. code like "variable += (a ? 1 : (b == 1 || c == 2) << 4));"). As a result, it was not possible to reach 100% branch coverage in such cases.

Enhancement

Instrumenter

TES-4614

Fixed parsing type declaration with missing space between key word and curly brace (e.g., enum{...}).

Instrumenter

TES-4647

A possibly incorrect case label in the coverage report has been fixed.

Release v4.2.23 (26 items)

Instrumenter

TES-4919

Fixed wrong coverage result if a function pointer in a call expression is guarded with superfluous parentheses. [e.g. (0 == structure ? 0 : (structure->pointer()))]

Interface Database (IDB)

TES-4660

Fixed stack overflow when reusing test objects with recursive structures.

Interface Database (IDB)

TES-5020

Fixed changed enum constant values in test data if the enum is not part of the test objects interface.

Parser

TES-4683

Fixed possible access violation with very huge structures in TESSY keyword scanner.

Test Database (TDB)

TES-4882

Fix that INOUT scalar values in dynamic objects are not saved when no IN value is set.

Test Database (TDB)

TES-5298

Fixed possible loss of pointer data when setting pointer data for a CTE tree node to an array element without test data.

Test Execution

TES-4910

Fixed possible test driver crash when executing with MC/DC coverage and a condition with a huge number of atoms is present.

Release v4.2.22 (15 items)

C++

TES-4467

Code to get/set members for a dynamic class was not generated when the class pointer is the component of a dynamic struct.

C++

TES-4482

Fixed error in generated test driver when a destructor was stubbed.

C++

TES-4542

Fixed possible assertion in parser when comparing declarations from different source files.

Release v4.2.22 (15 items)

Defines

TES-4527

Fixed parsing of a macro with another macro as value which is defined in another source file in the same module.

Driver

TES-4511

Fixed generated code for advanced stub with const pointer parameter.

Instrumenter

TES-4488

Fixed an access violation when instrumenting a declaration that spans multiple lines and contains preprocessor line information.

Instrumenter

TES-4512

Fixed syntax error in instrumented code when a casted tag type is returned and call pair coverage is active [e.g. return (enum E) value;]

Instrumenter

TES-4524

Fixed possible incorrect C0 coverage when there are superfluous curly braces around the function body [e.g. int test() {{... return 42;}}]

Interface Database (IDB)

Enhancement

TES-2212

Reduced high consumption of memory by interface database in case of huge structures being used.

Notes View

Enhancement

TES-2455

The notes view contents can now be exported as Excel XLSX format.

Notes View

Enhancement

TES-3390

Added "Find" menu entry to select the source element for a note within the Test Project view. Also fixed wordings and layout and added some shortcuts.

Parser

Enhancement

TES-4578

Use Compiler Install Path as default value for Header File Exclude List.

Script Editor

Enhancement

TES-2731

The module name is now suggested as file name in the script editor save dialog.

Test Execution

Enhancement

TES-4133

Added menu entry 'Debug Test' which executes the test with the 'Define Breakpoint' option set.

Release v4.2.22 (15 items)

Variant Management

TES-4468

Fixed possible incorrect assignment of test cases to a fault injection when creating a variant.

Release v4.2.21 (24 items)

C++

TES-4253

Fixed missing return type in stub code methods for constructors.

C++

TES-4274

Fixed setting break point at TESSY_TestobjectCall for C++ compilers that modify the function name with name mangling.

C++

TES-4280

Erroneous namespace was generated for method stubs, when the namespace contains a class with the same name as the namespace.

C++

TES-4290

Fixed generating stubs for functions in anonymous namespace.

CTE

TES-4060

CTE images will be generated during report generation and not during test execution.

Enhancement

Compiler/Target/Microcontroller

TES-4291

CodeWarrior plugin can now start the debugger automatically if required.

Enhancement

Compiler/Target/Microcontroller

TES-4329

Fixed Debugger Launch Path for TASKING VX.

Compiler/Target/Microcontroller

TES-4336

Updated configuration for default Keil installation path.

Enhancement

Driver

TES-4333

User defines where unknown in Fault Injection code.

Environment Editor (TEE)

TES-4446

If only flags of attributes were changed, a restart of TESSY was required to make them visible within the module properties.

Release v4.2.21 (24 items)

Instrumenter

TES-4399

Fixed instrumentation problem with 'for' loops when qualified data types (e.g. `std::vector<int>::size_type`) were used within the initialization part of the loop.

Interface Assigner (IDA)

TES-3167

Copy fault injections when assigning test objects in IDA.

Change function name in fault injections branch path, when the name of a called function changes.

Interface Assigner (IDA)

TES-4267

Fixed assigning renamed test object that already had a changed interface before.

Interface Database (IDB)

TES-4217

Added an option to create a simplified interface for struct/union with a very large number of components. Without this the parser runs out of memory while building the interface database. The new attribute 'Simplified Header Folder List' may be used to specify a comma separated list of directories. If inline functions are located in a header file residing in such a folder, the parser uses simplified tag type object for these functions. These functions can not be used as test objects and advanced stubs can not be used.

Enhancement

Interface Database (IDB)

TES-4353

Changing type declarations inside an anonymous union required a manual interface reuse although an automatic reuse was possible.

Interface Editor (TIE)

TES-4409

Advanced Stub Variables were displayed IRRELEVANT when the test object was a static class member function.

License Manager

TES-4278

Fixed taking into account `TESSYD_CI_LICENSE_FLAGS` environment variable.

Parser

TES-4023

Fixed possible incomplete structs in Interface Database when a module contains multiple source files where in one source a struct was declared abstract only.

Report

TES-4279

Show enums used in test data in the test object interface.

Enhancement

Script Editor

TES-4065

Support '*' in method signature for call trace in scripts.

Release v4.2.21 (24 items)

Script Editor

TES-4276

Correctly handle assignments and comparisons for function calls in scripts.

TESSY (General)

TES-4408

Reduced size of generated tks.exe files.

Enhancement

Test Data Editor (TDE)

TES-4251

Fixed error when entering the test object itself as function pointer target at void*.

Variant Management

TES-4245

Fixed that a CTE file must not be generated in a variant for a test object without a CTE file.

Release v4.2.20 (15 items)

ASAP Conversion

TES-4189

Fixed reading ASAP information for parameter in source files without global variables.

C++

TES-4218

Fixed parser error if a method gets a pointer of its class and accesses a member of a base class by that pointer.

C++

TES-4234

Fixed evaluation of class member targets when Attribute 'Generate Constructors' is false.

CTE

TES-4080

Fixed a runtime regression for saving CTE documents.

CTE

TES-4243

Fixed error message if CTE node cannot be attached to associated array index nodes.

Compiler/Target/Microcontroller

TES-4192

Fixed Wind River WindISS server script.

Compiler/Target/Microcontroller

TES-4203

New compiler Wind River ARM with Wind River WindISS simulator.

New Feature

Release v4.2.20 (15 items)

Defines

Enhancement

TES-4212

Improved performance of defines parser.

Driver

Enhancement

TES-4101

Stub code for local functions and C++ methods is generated to an own function at the end of a source file to avoid errors due to not declared types or variables at the location of the stubbed function.

Instrumenter

TES-4210

Failed to instrument function declared extern "C" and used as friend in a class.

Interface Editor (TIE)

TES-4135

Pass direction of non-static class member variables is always IRRELEVANT for static methods, since they can not be accessed by the method.

Parser

TES-4208

Fixed GNU Tools for ARM TKS template file concerning asm.

Test Data Editor (TDE)

TES-3943

After discarding changes in TIE the changes where not saved but still displayed in the GUI.

Test Data Editor (TDE)

TES-4104

Fixed error when entering the test object itself as function pointer target.

Test Data Editor (TDE)

TES-4235

Fix exception when searching partitioned arrays in TDE using "Find Value".

Release v4.2.19 (15 items)

Compiler/Target/Microcontroller

TES-3771

Updated tks_tasking_c166.h.

Compiler/Target/Microcontroller

Enhancement

TES-4059

Updated IAR TKS files regarding anonymous unions.

Compiler/Target/Microcontroller

Enhancement

TES-4084

Added static_assert rule to IAR TKS file.

Release v4.2.19 (15 items)

Compiler/Target/Microcontroller

TES-4154

Fixed special IAR number support.

Compiler/Target/Microcontroller

TES-4168

Fixed master script for the MetaWare debugger.

Component Test

TES-4132

A scenario containing only an INIT time step was marked as passed although containing failed eval macros.

Driver

TES-4150

Fixed generating driver for test objects with indirect recursive call.

Driver

TES-4162

Improved performance generating C++ test driver for modules containing large amounts of external classes.

Interface Assigner (IDA)

TES-3494

New dialog to move variables and functions that are not in the test objects initial interface to it.

Enhancement

Interface Assigner (IDA)

TES-4171

Fixed exception when double clicking a test object in the IDA perspective while a Compare View for its module is active.

Interface Database (IDB)

TES-4144

Fixed finding and assigning applicable unnamed enums during compare/reuse.

Parser

TES-4155

Updated Green Hills TKS files.

Enhancement

Parser

TES-4177

Fixed parsing of @-operator in tks-freescale.tpl

TESSY (General)

TES-4061

Expand modules bypassing analyze when using "Find" command on test objects in Status Dialog or Problems View.

Release v4.2.19 (15 items)

Variant Management

TES-4167

When synchronizing a variant module use of IDA was always required if the interface contained a structure with a recursive pointer.

Release v4.2.18 (60 items)

ASAP Conversion

Enhancement

TES-3979

Allow ASAP Conversion for parameters by setting attribute 'Enable ASAP Parameter' true. The parameter name should be unique, otherwise the conversion rule is applied to all parameter and global variables with this name.

Batch Operation

TES-3356

Apply report logo image and template path from TBS file when executing a batch test.

C++

TES-3987

Fixed loss of test data at members in recursive nested classes with base classes.

C++

TES-4029

Generate consistent script names for C++ test objects.

C++

TES-4045

Fixed an incorrect interface database when using a structure declared inside a class as a parameter of a template function.

CTE

New Feature

TES-3789

The classification tree generation now considers variables with ASAP information available. Class nodes with physical values for minimum and maximum will be created in any case. For unsigned values a node for a mean value will be calculated and for signed values nodes for physical representation of -1, 0 and 1 will be created if they match the defined ASAP range.

CTE

TES-3959

Missing or wrong array indices in CTE data generation assigned test data for every array element. Accidentally generated test data will now be removed if the respective node is fixed by the user. Wrong or missing array indices will now cause error messages.

The CTE will now also generate nodes for multi dimensional arrays.

CTE

TES-4050

Fix indirectly called methods are not generated in the called functions sub tree of the automatic CTE document.

Release v4.2.18 (60 items)

CTE

TES-4055

Fixed that test sequences in migrated CTE documents were not correctly synchronized.

CTE

TES-4073

TESSY prevents now that copied test projects with custom folder layout get inconsistent CTE documents.

CTE

TES-4092

Fix some errors during saving scripts of test objects with CTE data.

CTE

TES-4094

CTE-554: A new test sequence has now automatically added the first test step.

New Feature

Command Line (tessycmd)

TES-3944

TESSYD --version now shows correct version information.

Compiler/Target/Microcontroller

TES-3972

Fixed Microchip MPLAB X for XC32 Makefile template.

Compiler/Target/Microcontroller

TES-3985

Fixed ts_make_trace32_taskingvx30_tricore.tpl.

Compiler/Target/Microcontroller

TES-3996

Fix winIDEA Makefile templates for Cosmic S12 and TI Arm.

Compiler/Target/Microcontroller

TES-3999

Fixed IDB Makefile for the Microchip XC8 compiler.

Compiler/Target/Microcontroller

TES-4014

Fixed "Check Source" feature for the new TASKING compilers.

Compiler/Target/Microcontroller

TES-4028

Updated communication interface to UDE target (AtsUdeInterface.dll to version 4.2.0.1).

Enhancement

Coverage Viewer (CV)

TES-4032

Fixed Coverage Viewer initialization being triggered unnecessarily.

Release v4.2.18 (60 items)

Driver

TES-2603

Fixed possible error generating a test driver after deleting a synthetic variable also used by the function under test in a different test object.

Driver

TES-3295

UTF-8 byte order marks at the beginning of a source file will now be removed when generating the test driver.

Instrumenter

TES-3973

If a static local variable of a tag type declared only in the function under test was used, then with call pair coverage (CPC) measurement turned on, the generated driver was syntactically incorrect.

Instrumenter

TES-3981

Fixed possible missing struct/union/enum keyword in the instrumented code when Call Pair Coverage (CPC) is enabled.

Instrumenter

TES-4034

The possible absence of the ';' after a break statement resulted in a non-executable test with call pair coverage (CPC) enabled.

Instrumenter

TES-4054

Fixed incorrect instrumentation of an expression that uses a pointer to array cast (e.g. (char (*)[42]) NULL == variable).

Instrumenter

TES-4056

If call pair coverage (CPC) is enabled, the "Instrumentation Exclude List" attribute was not handled correctly and resulted in a lower C1/C2 coverage measurement result than actually achieved being reported.

Interface Database (IDB)

Enhancement

TES-3860

Improved performance restoring module backups.

Interface Database (IDB)

TES-3903

Loss of test data at struct member that was actually IRRELEVANT after changing its name.

Interface Database (IDB)

Enhancement

TES-3975

Enhanced automatic reuse in special situations for unit tests: When comparing called functions and the test object has no call trace and the unassigned called functions are not stubbed, an automatic reuse will be done.

Release v4.2.18 (60 items)

Interface Database (IDB)

TES-4099

Fixed possible file access error on a CI System running with full load and with security software running in background.

Interface Database (IDB)

TES-4120

Automatic reuse of test objects where a constant of an enum parameter/return of a called function changes.

Makefile Templates

TES-4083

Fixed communication Makefile for PLS UDE / TI TMS 570.

Parser

TES-4105

Fixed handling IAR localized integer format.

Project Handling

TES-4072

Do not require modules to be analyzed again after editing unrelated project settings.

Report

TES-4098

Fixed generating overview report for not executed component tests.

Requirements

TES-4025

Bugfix to enable the creation of a requirement document hierarchy again.

Save/Restore Database (TMB Files)

TES-2334

Save notes for component tests during database backup.

Scenario Editor (SCE)

TES-4097

Fixed error during (automatic) reuse of a Component Test from older versions of TESSY due to remnants of deleted time steps in the test database.

Script Editor

TES-3408

Support '~' operator in script expressions.

Script Editor

TES-3894

Write fault injection test cases in script.

Script Editor

TES-3941

Improve formatting of evaluation macros in scripts.

Release v4.2.18 (60 items)

Script Editor

TES-4071

Correctly recognize inactive union components as interface variables in Script Editor.

TESSY (General)

TES-2540

Add context menu to "Test Directory" section in Properties View.

Enhancement

TESSY (General)

TES-3246

Add notice that description, specification and comment for folders and test collections are not included in database backup.

Enhancement

TESSY (General)

TES-3479

Support key binding "Ctrl+A" in code editors.

Enhancement

TESSY (General)

TES-3896

Properties view, attributes tab: Fixed menu entries "Copy to Configuration Folder" and "Open with Editor/Application" for file type attributes with values containing references to other attributes of the environment.

Enhancement

TESSY (General)

TES-3952

Updated the windIDEA OBTI connection.

TESSY (General)

TES-4011

Fix error message "Entity does not exist" when updating the Test Data Editor or Test Definition View.

TESSY (General)

TES-4066

Show error message when attempting to analyze modules containing test objects with names longer than 1024 characters.

Test Data Editor (TDE)

TES-2909

Refresh filter results in Test Data Editor when changing perspectives.

Test Data Editor (TDE)

TES-4003

Fix Inputs and Outputs being collapsed in Test Data Editor when "Link with test item view" and "Hide ignored variables" are both active.

Test Database (TDB)

TES-3971

Fixed booting database on Turkish Windows.

Release v4.2.18 (60 items)

Test Database (TDB)

TES-4040

A possible null pointer exception when displaying historical test data has been fixed.

Variant Management

TES-4043

Do not execute deleted variant test steps.

Variant Management

TES-4077

Missing stub code in variant module if a manual assignment of the interface was necessary during synchronization.

Variant Management

TES-4079

Fix exception when replacing a missing parent module in the Properties View.

Variant Management

TES-4113

Fixed erroneous synchronization warning after saving/restoring of module TMB backups (caused by updates of the last modified time stamp of parent modules). This problem was introduced with TES-3707 in TESSY v4.1.29, v4.2.15 and v4.3.6.

Variant Management

TES-4116

Fixed incorrect progress when synchronizing multiple modules at once.

Variant Management

TES-4117

Improved error reporting when creating variant modules.

Enhancement

Release v4.2.17 (21 items)

C++

TES-3964

Fixed possible duplicate IDs in interface databases, which in some cases may lead to undefined behavior when entering test data or executing a test.

Compiler/Target/Microcontroller

TES-3560

Added attribute 'Library Path' to the configuration of combination TASKING TriCore VX / Lauterbach Trace32.

Enhancement

Component Test

TES-3961

Fixed setting initial passing of scenario variables.

Release v4.2.17 (21 items)

Defines

TES-3918

Consider value suffix u/U when calculating define values.

Instrumenter

TES-3930

Fixed instrumenting statements containing cast to pointer to array.

Interface Database (IDB)

TES-3919

Implemented meaningful progress for module analysis.

Enhancement

Interface Database (IDB)

TES-3934

Find and assign applicable unnamed enums during compare/reuse.

Enhancement

Interface Editor (TIE)

TES-3054

Do not show anonymous enums/structs/unions within the "New Variable" dialog. Also allow defines to be used as values for the array dimensions.

Enhancement

Metrics

TES-3920

Fixed problems when importing actual time values and enhanced error message handling within the dialog.

Parser

TES-3917

Updated TKS configuration for HighTec TriCore.

Parser

TES-3926

Fixed high memory usage when many external functions have huge structures as parameter.

Parser

TES-3927

Fixed rarely occurring analyzing loop.

Parser

TES-3931

Fixed error when processing more than 255 command-line arguments.

Parser

TES-3950

Reduced memory consumption while analyzing source files.

Project Handling

TES-3940

Improved validation in "New/Edit Project" dialog.

Enhancement

Release v4.2.17 (21 items)

Report

New Feature

TES-2097

Added last modified time stamp as optional report content for test overview and test details report.

TESSY (General)

New Feature

TES-3922

Added sample project and sample TMB file.

Test Data Editor (TDE)

Enhancement

TES-3597

Added preference option to hide ignored variables (those with value *none*) in TDE when filtering test items using the "Link with Test Item View" button.

Test Data Editor (TDE)

TES-3898

Fix exception when invoking "Next/Previous Failed Value" in Test Data Editor in specific situations.

Test Data Editor (TDE)

TES-3909

Fixed entering defines containing a hexadecimal number in their name.

Variant Management

TES-3966

Assignment of variables for synchronizing variant modules got lost, when the modules source file(s) path was different due to changed project location (e.g. when running a project on a different computer).

Release v4.2.16 (11 items)

Command Line (tessycmd)

Enhancement

TES-3872

Log any forced auto-reuse operations carried out for test objects with changed interfaces in headless mode.

Command Line (tessycmd)

TES-3873

Apply attribute 'Function Stub Exclude List' when automatically stubbing new external functions in headless mode and apply 'Variable Exclude List' when automatically defining new variables in headless mode.

Driver

TES-3878

Fixed generating driver for test objects with function local static pointers.

Driver

TES-3895

Fixed generating declaration of function pointer using an enum parameter defined inside a class.

Interface Database (IDB)

Enhancement

TES-3871

Changes in enum values will not require a manual reuse anymore, the new values will be applied automatically.

Release v4.2.16 (11 items)

TESSY (General)

New Feature

TES-2647

Added feature to import actual time values from a given TESSY overview report XML file.

TESSY (General)

TES-3874

Fix file contexts leading to problems log failing to open.

TESSY (General)

Enhancement

TES-3880

Enhanced performance of toolbar and menu item sensitivity handling in graphical user interface.

Test Data Editor (TDE)

TES-3902

Set new vector size when using actual as expected on an advanced stub vector value.

Test Data Editor (TDE)

TES-3910

Fixed opening combo box to enter value for 'throws exception'.

Variant Management

Enhancement

TES-3079

Show full path name of variants within parent variant selection combo box.

Release v4.2.15 (55 items)

ASAP Conversion

TES-3792

Fixed error executing ASAP Parser, when the database location is APPDATA or USERPROFILE.

ASAP Conversion

TES-3816

Fixed validation problem with TAB_VERB values during reuse operation on interface changes.

C++

TES-1856

Fixed testing of static methods.

C++

TES-3736

Possible parser error if recursive structures without a tag name are used.

C++

TES-3750

Fixed instrumenting constructor preceded by an explicit deleted copy constructor.

Release v4.2.15 (55 items)

C++

TES-3840

Fixed parser error when using templates with variadic parameter as base class.

C++

TES-3849

Fixed generating type modifier for reference to array.

CTE

TES-3831

CTE-171 Now its possible to show/hide/create/delete/move automatic and manual page breaks in the test table to predefine the content for table pages. Now the image exporter exports each table page as separate image.

Enhancement

CTE

TES-3832

Fix issue where CTE documents of test objects with arrays of structures are not saveable.

CTE

TES-3850

Fix an issue where CTE documents are not correctly saved when pointers to unions only have an address value.

Command Line (tessycmd)

TES-3852

Fixed potential errors when importing requirement documents via command line.

Compiler/Target/Microcontroller

TES-3727

Updated default compiler dialect for GNU Tools for ARM Makefile templates.

Compiler/Target/Microcontroller

TES-3753

Added inline functions from mingw header files to 'Test Object Exclude List' attribute in 'GNU GCC' environment.

Compiler/Target/Microcontroller

TES-3755

Fixed TRACE32 slave file to avoid a warning.

Compiler/Target/Microcontroller

TES-3759

Add C++ support for ARM V6.

New Feature

Compiler/Target/Microcontroller

TES-3775

Fixed TKS template for IAR 78K and IAR 78K V4.

Compiler/Target/Microcontroller

TES-3809

Fixed UUIDs for TI Code Composer 9 combinations.

Release v4.2.15 (55 items)

Compiler/Target/Microcontroller

TES-3821

Fixed ti ARM IDB Makefiles concerning include paths.

Compiler/Target/Microcontroller

TES-3822

Added missing timer file feature to uVision UVSC communication Makefile.

Compiler/Target/Microcontroller

TES-3823

Fixed IDB Makefile for the Keil compiler.

Compiler/Target/Microcontroller

TES-3827

Updated and corrected the winIDEA adaption.

Compiler/Target/Microcontroller

TES-3830

Updated TKS file for the Keil compiler.

Coverage Measurement

TES-3855

Added missing attributes for CPC coverage to default configuration.

Defines

TES-3829

Fixed possible missing defines referencing other defines.

Driver

TES-3729

Fixed generating namespace name for a type defined in a base class in a different namespace.

Driver

TES-3780

Fixed sending data for constructor parameter that is a struct with an array of structs as member.

Driver

TES-3786

Fixed initialization of enum return in unused extern stub functions in C++ tests.

Driver

TES-3804

Generate code to initialize addresses in slave to correct source file.

Driver

TES-3841

Fixed function name conflict in slave if the test contains a reference to a class named 'parameter'.

Release v4.2.15 (55 items)

Import/Export

TES-1805

Fixed importing advanced stub variables to C++ test objects.

Import/Export

TES-3185

Find and move variables to test object interface on import of test data.

Enhancement

Import/Export

TES-3731

Fixed importing dynamic object of pointer in struct array.

Import/Export

TES-3747

Move unused to used functions during import.

Import/Export

TES-3806

Fixed export of vector values for advanced stub variables containing enum or define constants (e.g. "{A,B,C}").

Instrumenter

TES-3193

Added support to test operators "new" and "delete" with instrumentation.

Instrumenter

TES-3777

Fixed instrumentation of constructors.

Interface Assigner (IDA)

TES-3798

Changes of array sizes will not trigger a reuse operation.

Interface Database (IDB)

TES-3782

Anonymous unions will now be handled as global variables.

Interface Database (IDB)

TES-3826

Possible failure to open large Interface Database after analyze when an antivirus software is running.

Parser

TES-3734

Fixed scanner call for IAR RX.

Parser

TES-3735

Sources containing only declarations and no functions where successfully analyzed.

Release v4.2.15 (55 items)

Parser

TES-3812

Implemented support for 32 bit unsigned enum constants.

Parser

TES-3838

Fixed importing Doxygen specifications if Doxygen emits functions to multiple files. Also added boolean attribute 'Doxygen Ignore Includes' to let Doxygen ignore the include paths.

Report

TES-2860

Added specification, description and comment of test collections, folders, modules and test objects as optional content into the overview report. **New Feature**

Report

TES-3839

Attempt to automatically resolve file name conflicts during report generation, and display an error message if the report file name pattern is configured such that automatic resolution is not possible.

Report

TES-3847

Fixed memory leak during report generation.

Requirements

TES-3853

Fixed potential exception when loading requirement documents containing deleted requirements.

Save/Restore Database (TMB Files)

TES-3707

Added time stamp update for modules after save/restore TMB backup files to prevent save request when closing TESSY. **Enhancement**

Save/Restore Database (TMB Files)

TES-3733

Include paths were not shown in "Sources" tab after restoring a TMB file.

TESSY (General)

TES-3728

Always open internal editor when using "Open With Editor". **Enhancement**

TESSY (General)

TES-3749

Test objects were missing in module backups of modules that currently failed to analyze, but that were analyzed in the past.

Test Data Editor (TDE)

TES-3748

An error message will now be issued if advanced stub vector values are entered for struct/union members (which is not supported). **Enhancement**

Release v4.2.15 (55 items)

Test Database (TDB)

TES-3810

Fixed loss of pointer test data when the target is a multi dimensional array, but given with less dimensions.

Test Evaluation

TES-3758

Fixed evaluating dynamic OUT variables for targets using file communication.

Test Execution

TES-3846

Fixed memory leak during test execution and evaluation.

Release v4.2.14 (9 items)

C++

TES-3714

Fixed error in generated driver for function with template parameter.

CTE

TES-3704

Fixed an missing update of the advanced stub call vector size when using vector values (e.g. "{1,2,3}").

CTE

TES-3705

Fixed problem with dynamic objects: Dynamic test data entries were deleted in CTE when not referenced by a pointer in the same CTE node.

Compiler/Target/Microcontroller

Enhancement

TES-3657

Reduced test execution time for NXP (former Freescale) CodeWarrior 10/11.

Compiler/Target/Microcontroller

TES-3713

Fixed Makefile template for GNU Tools for ARM with TRACE32.

Compiler/Target/Microcontroller

Enhancement

TES-3719

Implemented optional SOFT breakpoints for TRACE32's timer feature.

Driver

TES-3715

Fixed possible error generating driver if a pointer targets a dynamic object created at another pointer in "Inputs" section of TDE and a normal target in "Outputs" section or vice versa.

Interface Editor (TIE)

TES-3722

If a class members was set to EXTERN all members might become EXTERN when loading the test object again.

Release v4.2.14 (9 items)

Test Execution

TES-3708

Fixed possible error generating report during batch test execution when advanced stubs are used for other test objects called by the test object under test.

Release v4.2.13 (35 items)

ASAP Conversion

TES-3680

Fixed reuse of expressions in modules where ASAP is enabled.

C++

TES-3619

Fixed problem testing functions using a class where a member variable and an inherited member variable have an equal name.

CTE

TES-3672

CTE-536 Fix an error in the image export of CTE diagrams grey as default color in the view showing the root node.

CTE

TES-3686

Fixed saving values for union components.

Compiler/Target/Microcontroller

New Feature

TES-3578

Added C++ support for IAR 8051.

Compiler/Target/Microcontroller

New Feature

TES-3610

New combination for HighTec TriCore compiler and TASKING VX debugger.

Compiler/Target/Microcontroller

TES-3621

Fixed Microchip dsPIC configuration regarding Object Module Format.

Compiler/Target/Microcontroller

Enhancement

TES-3644

Implemented support of Check Driver Layers type test for 16 bit targets.

Compiler/Target/Microcontroller

TES-3647

Fixed building of board files in Renesas RX(++) e2studio Makefile templates.

Compiler/Target/Microcontroller

New Feature

TES-3648

Added C++ support for IAR RX.

Release v4.2.13 (35 items)**Compiler/Target/Microcontroller***Enhancement*

TES-3649

Added File Compression support for 16 bit character targets.

Compiler/Target/Microcontroller

TES-3650

Fixed Check Driver Layers feature for Green Hills MULTI.

Compiler/Target/Microcontroller*Enhancement*

TES-3666

Implemented parallel execution support for TASKING VX. Set attribute "Target Concurrency" to 1 when using hardware.

Compiler/Target/Microcontroller

TES-3677

Fixed possible compile time error concerning `tstcomm_send_compress()`.**Compiler/Target/Microcontroller***Enhancement*

TES-3695

Changed default optimization in TEE attribute Tricore Compiler Options to no optimization.

Defines

TES-3661

Fixed possible access violation in defines parser.

Driver

TES-2790

Fixed erroneously generated test driver for anonymous unions in IAR compiler headers.

Driver

TES-3039

Fixed evaluation of reference member variables.

Driver

TES-3625

Fixed terminating master after slave exits with error.

Driver

TES-3629

Fixed possible missing function prototypes in generated slave source files in modules with multiple source files.

Driver

TES-3667

Fixed erroneous namespace for inner struct in class used as parameter for a constructor of a class in a different namespace.

Release v4.2.13 (35 items)

Driver

TES-3687

Fixed generating advanced stub variable declarations with typedef names containing 'struct', 'union' or 'enum' as part of the name.

Instrumenter

TES-3626

Fixed wrongly instrumented code for CPC coverage in case of a switch expression that was surrounded with additional parentheses.

Instrumenter

TES-3673

The module attribute "Instrumentation Exclude List" was not working for inline functions.

Interface Database (IDB)

TES-3630

Possible wrong call trace and/or stub code if template functions were used.

Interface Database (IDB)

TES-3631

Exclude template functions as test objects.

Parser

TES-3671

Fixed parsing source using `_Static_assert` with legacy parser.

Script Editor

TES-3623

Fixed erroneous test data status (grey test cases) in case of unused dynamic objects still present within script inputs section.

Script Editor

TES-3662

Correctly parse multiline strings with Unix EOL in scripts.

TESSY (General)

TES-3639

Add filter text in Attribute Section in Properties View.

Enhancement

TESSY (General)

TES-3668

Fixed potentially suppressed error messages within the messages view.

Test Data Editor (TDE)

TES-3642

Fixed "Copy Actual Value" for arrays.

Release v4.2.13 (35 items)

Test Database (TDB)

TES-3627

Fixed missing values of dynamic objects (that have passing OUT only) if a new dynamic object was created after a new test case was added.

Test Database (TDB)

TES-3654

Fixed copying inherited test steps within the test items view. Inherited test data has not been copied to the newly pasted test steps.

Variant Management

TES-3640

Corrected behavior for overwriting inherited test cases.

Release v4.2.12 (26 items)

C++

TES-3576

Fixed parser crash if a call expression is used to initialize an enumeration value.

CTE

TES-3496

Fix an issue where CTE documents for scenario tests seem to have test data for CTE nodes. CTE documents in scenario tests never provide test data, these have to be declared in the TDB view.

CTE

TES-3565

Fix the execution result icon in the CTE is not synchron with the icon in the project view.

CTE

TES-3604

CTE-530 Fix replacing a string with the empty string is not allowed.
CTE-521 Fix some problems with the find next/previous button in the CTEs find dialog.
CTE-523 Fixed wrong initial path in save to dialog
CTE-172 Now warning decorations will also be attached to dependencies.
CTE-516 The CTEs search result view has now a refresh button.
CTE-467 Now it is also possible to show only relevant or transitive relevant dependencies.
CTE-466 The line from a leaf class to its mark was not correctly aligned for some special cases.
CTE-495 CTE has now a context menu entry to delete all styles of the selected object. Remark: Inherited styles are not affected by this.
CTE-518 Fix that the number of test cases in nested groups is zero.
CTE-377 Fix the mark of a white class between two colored classes is not white but has the color of the left class.
CTE-483 Now leaf class sorting feature based on the node name is available.
CTE-512 Fix error when migrating legacy CTE files with refinements without content.

New Feature

Compiler/Target/Microcontroller

TES-2427

Changed communication technique for the MetaWare debugger to improve execution speed. Please, refer to the application note for further important hints.

Enhancement

Release v4.2.12 (26 items)**Compiler/Target/Microcontroller****Enhancement**

TES-3556

Updated GNU Tools for ARM TKS file and Makefile template.

Compiler/Target/Microcontroller

TES-3564

Fixed THAI for GCC/CDT.

Compiler/Target/Microcontroller

TES-3566

Added backward compatibility for older Keil (X)C166 compilers.

Compiler/Target/Microcontroller**Enhancement**

TES-3575

The communication type for the e2 studio adaption changed to file communication. Please open TEE once and save the configuration.

Compiler/Target/Microcontroller

TES-3577

Fixed built-in module, which failed to compile using the callback function.

Compiler/Target/Microcontroller**Enhancement**

TES-3588

Updated IAR TKS template file.

Compiler/Target/Microcontroller**New Feature**

TES-3592

Added Makefile template for TASKING ARM and Lauterbach TRACE32 to use the carm compiler instead of ccarm.

Compiler/Target/Microcontroller**Enhancement**

TES-3595

Implemented file communication for Green Hills MULTI. Please read the application note for important instructions!

Compiler/Target/Microcontroller

TES-3606

Added missing UDE master object file.

Component Test

TES-3558

Fixed error in test driver if a mode variable is used that is not defined in the first source file.

Driver

TES-3591

Fixed possible crash when generating the test driver for a component test.

Release v4.2.12 (26 items)

Import/Export

Enhancement

TES-3616

PTU import now supports range based indices for arrays, e.g. ARRAY myArray[0..9], INIT = { 0..8 => 5, others => 0}

Interface Database (IDB)

TES-3573

Fixed opening module if calculated MCC exceeds 9223372036854775807.

Interface Database (IDB)

TES-3611

Fixed false negative message that a dynamic object has been removed when auto reusing a test object.

Parser

TES-3617

Fixed detecting pass direction of dereferenced struct pointer components. This changed behavior of the parser can be disabled to keep compatibility with earlier TESSY v4.x minor versions by adding a boolean type attribute "Disable TES-3617" into the TEE configuration of your project with a value of "true".

TESSY (General)

Enhancement

TES-3505

Toggle check boxes in the test object filter dialog using the space key.

TESSY (General)

TES-3563

Fixed preferences occasionally being reset to their default values when starting TESSY.

TESSY (General)

TES-3614

Fixed missing refresh of compiler includes/defines after updates of TEE environments. The module properties still showed old inherited values and those old values were also written into the control files for module analysis.

Test Data Editor (TDE)

TES-3585

Fixed possible error with advanced stub variables after analyze in test object in called function using const variables.

Test Data Editor (TDE)

TES-3596

Automatically make matching array elements visible when searching for the next/previous passed/failed/undefined value in the test data editor.

Variant Management

Enhancement

TES-3590

Inherit/overwrite description and specification for variant modules and test items.

Release v4.2.11 (30 items)

ASAP Conversion

Enhancement

TES-3504

Added new attribute "Enable ASAP Test File" (default: true) to enable/disable loading of ASAP test file.

ASAP Conversion

TES-3523

The attribute "Float Eval Epsilon" is not applied any more to physical integer values.

ASAP Conversion

TES-3552

Fixed missing MIN/MAX values within ASAP properties if the environment variable ASAP_IGNORE_FORMAT_FOR_MIN_MAX was used.

C++

TES-3503

Default constructors for STL classes will not be generated into the test driver application any more.

Compiler/Target/Microcontroller

Enhancement

TES-3458

Updated TKS file for Microchip compilers.

Compiler/Target/Microcontroller

Enhancement

TES-3463

Significantly diminished test execution time using PLS UDE.

Compiler/Target/Microcontroller

TES-3481

Fixed timer file feature in communication Makefiles and Makefile templates.

Compiler/Target/Microcontroller

TES-3489

Updated MPLAB X TESSY target handler to support ATSAMD21G17D.

Compiler/Target/Microcontroller

TES-3513

Fixed THAI implementation in combination with file communication.

Compiler/Target/Microcontroller

Enhancement

TES-3526

IAR ARM was set to obsolete. It was replaced by IAR ARM V5 long ago.

Compiler/Target/Microcontroller

Enhancement

TES-3536

Set attribute "Post Execution Command" for MPLAB and set attribute "Quit Target Handler" to false.

Compiler/Target/Microcontroller

TES-3538

Fixed Microchip XC32 Makefile templates regarding linker script option.

Release v4.2.11 (30 items)

Compiler/Target/Microcontroller

Enhancement

TES-3540

Updated GNU ARM TKS file.

Compiler/Target/Microcontroller

TES-3544

Fixed type table file link for Linaro GNU ARM C++.

Compiler/Target/Microcontroller

Enhancement

TES-3546

TEE attribute "Method Stub Exclude List" was set to std::* by default.

Compiler/Target/Microcontroller

TES-3548

Fixed some bugs regarding Synopsys MetaWare debugger and added support for parallel execution.

Driver

Enhancement

TES-3506

Enabled Attribute 'Synthetic Declarations In Source' for CLANG driver.

Import/Export

TES-2034

Fixed importing test data for dynamic objects for

- pointer to pointer
- dynamic structs with struct array component
- dynamic objects from pointer components inside dynamic array of structs

Instrumenter

TES-3553

Fixed CPC instrumentation when sizeof() is used as parameter for a function call.

Interface Editor (TIE)

Enhancement

TES-3266

Disabled 'Use In Report' for IRRELEVANT variables.

Interface Editor (TIE)

TES-3539

Allow passing IN for a parameter reference to class without members.

Parser

TES-3480

Fixed TKS file for Keil C166 and C51 compilers.

Parser

Enhancement

TES-3508

Added CLANG support for Synopsys DesignWare and MetaWare compilers.

Release v4.2.11 (30 items)

Parser

TES-3519

Fixed TKS file for IAR concerning va_list.

Parser

TES-3528

Updated TKS file for ARM V5.

Parser

TES-3543

If a struct without a tagname is used as recursion pointer target, the parser was unable to find the pointer target type id.

Requirements

Enhancement

TES-1881

Added import/export of link matrix in XML format.

Script Editor

TES-3545

Fix test steps with unused dynamic objects not being executable after committing the script editor.

TESSY (General)

Enhancement

TES-3532

Added support for UNC paths including the user appdata directory.

Test Evaluation

TES-3530

The "Float Eval Epsilon" attribute will now also be applied for float values when using the eval mode "not equal". A deviation within the epsilon range will be evaluated as failed (e.g. an actual value of 1.009 will be failed for an expected value of !=1.0 if the epsilon is 0.01).

Release v4.2.10 (24 items)

ASAP Conversion

TES-3487

Fixed parse error for A2L files containing "\\\" as string.

CTE

Enhancement

TES-3128

Now "Find CTE Validation Issues" context menu entry is available in the document tree view to find validation issues in CTE documents referenced by test objects. Results will be listed in the problems view.

CTE

TES-3373

Now a classification is generated for a nested enum in (pointer to) structure.

Release v4.2.10 (24 items)**CTE**

TES-3459

Fix CTE opens for test objects with incomplete interface.

CTE

TES-3464

Fixed an error which prevents the update of the result status of CTE test case icons.

*Enhancement***CTE**

TES-3474

Fix interface elements are still associated with CTE node after setting passing to "IRRELEVANT".

CTE

TES-3475

TESSY will now show a warning if a CTE file specified for a test object does not exist.

Command Line (tessycmd)

TES-3491

TESSYD failed to stop the running instance if TESSY is installed inside a folder that resides on a drive created with 'subst'.

*Enhancement***Compiler/Target/Microcontroller**

TES-3423

Added "defines" support for Microchip AVR IDB Makefile.

*Enhancement***Compiler/Target/Microcontroller**

TES-3444

Keil ARMv5 IDB Makefile now supports preprocessing source files with doxygen comments.

Compiler/Target/Microcontroller

TES-3447

Updated IAR ARM V5 Makefiles.

*Enhancement***Compiler/Target/Microcontroller**

TES-3451

Updated IAR RL78 V2 configurations.

*Enhancement***Compiler/Target/Microcontroller**

TES-3456

Implemented File Communication for PLS UDE.

*Enhancement***Compiler/Target/Microcontroller**

TES-3465

New combination of GNU Tools for ARM compiler with iSYSTEM winIDEA debugger.

*Enhancement***Compiler/Target/Microcontroller**

TES-3495

Adapted IDB Makefile for XC8-CC to support the latest compiler version.

Enhancement

Release v4.2.10 (24 items)

Defines

TES-3486

Fixed possible wrong calculation of 64 bit integer expressions and defines.

Instrumenter

TES-3469

Insert User Declarations to source file if test runs with fault injection.

Instrumenter

TES-3501

The instrumenter failed to find the test object if a class or struct is present that initializes a field using an alignof operator.

Parser

TES-3482

Fixed problem in idb-arm-gcc.mak that occurred when parsing multiple source files.

Parser

TES-3490

Fixed finding doxygen specification for functions if the doxygen feature 'grouping' is used.

Requirements

TES-3492

Added UUID of modules, test objects and test cases into Excel export of link matrix. Also added Excel import function that creates links for the elements available within the link matrix.

Enhancement

Save/Restore Database (TMB Files)

TES-3473

Fixed non-functional "No" button within save modules dialog when closing TESSY.

TESSY (General)

TES-3472

Generate doxygen specification although doxygen has written an error log file.

Test Execution

TES-3499

Fixed potential deadlock during test execution.

Release v4.2.9 (34 items)

CTE

TES-2020

Now the CTE migration dialog remembers the user decision

Enhancement

CTE

TES-3368

Fixed generating pointer value classes for *min* and *max* values (now without parentheses which caused the generated test data for pointer values being invalid).

Release v4.2.9 (34 items)**CTE**

TES-3376

Fix missing CTE node name to test data generation for pointer parameters with INOUT target passing.

CTE

TES-3378

Fix that the "CTE Node name to test data" evaluates macros instead of saving the macro expression.

CTE

TES-3392

Extended generated 'Return' node subtree in external function call when structure is returned.

CTE

TES-3415

Enhanced node name wording for generated min/max class nodes.

Enhancement**CTE**

TES-3429

Fixed a NPE when saving the CTE after deleting a tree node.

CTE

TES-3430

Optimized the CTE save process.

CTE

TES-3439

CTE_505 Now some more space was added to the table bottom to optimize better context menu handling

CTE_507 The Search Result View allows now to replace the text in the selected or in all rows.

CTE_512 Fix error when migrating legacy CTE files with refinements without content.

CTE_444 Optimized mark cursor positioning when switching between refinements.

CTE_511 Fix error with copy and paste refinements.

Compiler/Target/Microcontroller

TES-2047

Enabled CLANG support for IAR STM8 by default.

Enhancement**Compiler/Target/Microcontroller**

TES-2367

Added CLANG support for Keil compilers.

Enhancement**Compiler/Target/Microcontroller**

TES-3354

Updated Microchip XC8 TKS file to remove interrupt attributes.

Enhancement**Compiler/Target/Microcontroller**

TES-3366

Fixed defines problem for Fujitsu FFMC32/FFMC16 compiler.

Release v4.2.9 (34 items)

Compiler/Target/Microcontroller

TES-3389

Fixed duplicate defines header feature, which failed for paths containing spaces.

Compiler/Target/Microcontroller

TES-3428

Fixed Makefile templates for Green Hills/e2studio and HighTec TriCore/TRACE32/winIDEA which contain TASKING_HOME by mistake.

Compiler/Target/Microcontroller

TES-3434

Fixed problem that may occur when switching between socket and file communication with TRACE32. Please remove all TS_SUPPORT_SCRIPT defines from your project's Makefile templates.

Component Test

TES-3443

Test was executable although no work task was selected.

Coverage Measurement

Enhancement

TES-2988

Added attribute 'Instrumentation Exclude List' to specify functions to be excluded from coverage measurement.

Defines

TES-3374

Added attribute "Define Value Collapse Exclude List" to exclude defines from being collapsed.

Driver

TES-3355

Fixed generated code for array with pointers to array with pointers of any type.

Driver

TES-3394

Fixed generating enum initialization for C++ standard 98 and 03.

Driver

TES-3411

Fixed crash of master after slave signals an error.

Instrumenter

TES-3425

Fixed instrumenting methods after an access specifier following a deleted function.

Instrumenter

TES-3427

Fixed erroneous call pair coverage code at asm(...) statements.

Interface Assigner (IDA)

TES-3401

Fixed assignment of test objects with CTE specification containing references to interface objects.

Release v4.2.9 (34 items)

Interface Database (IDB)

Enhancement

TES-3370

When CLANG is enabled unknown array sizes are now ignored if the array is IRRELEVANT.

Interface Database (IDB)

TES-3377

Fixed initial passing of new componts in advanced stub struct variable.

Interface Database (IDB)

TES-3436

Fixed problem with comments in defines for Keil ARM v5 IDB Makefile.

Interface Editor (TIE)

TES-3369

Allow editing unknown array size at advanced stub variables.

Makefile Templates

TES-3391

Fixed include option for TI ARM IDB Makefile.

Parser

TES-3381

Fixed recognizing integer type and size of typedefs using mode attribute for Microchip AVR compiler.

Parser

TES-3426

Fixed parsing `__attribute__((__vector_size__(x)))`.

Scenario Editor (SCE)

TES-3433

Removed sorting of work tasks when saving a scenario.

Script Editor

Enhancement

TES-3384

Enhanced syntax error messages when importing script files.

Release v4.2.8 (41 items)

C++

Enhancement

TES-3263

Fixed possible invalid interface database if enum types are declared inside a class.

C++

TES-3310

Fixed generating helper variable names for advanced stub functions if an overloaded operator is used as advanced stub.

Release v4.2.8 (41 items)**CTE**

TES-3233

Now synthetic variables are considered for tree generation by default.

*Enhancement***CTE**

TES-3282

CTE_508 FIX error during batch exports.

CTE_506 FIX error after closing an refinement editor.

CTE_509 Reduce low level parallelization which leads to deadlocks in some cases.

CTE_499 Fixed random sorting of table entries on drag&drop operation

CTE_93 Now a search dialog is available to find strings in tree nodes and table entries.

CTE

TES-3309

Fixed generating CTE for interface containing only external and no other global variables.

CTE

TES-3337

Fixed restoring module with CTE file located outside database folder.

Compiler/Target/Microcontroller

TES-2939

New NXP Clang compiler with NXP Smart Card Composer's gdbserver as debugger.

*New Feature***Compiler/Target/Microcontroller**

TES-3205

Fixed tks file for TASKING TriCore: remove __align from analyzing.

*Enhancement***Compiler/Target/Microcontroller**

TES-3206

Fix pragma asm problem in Green Hills tks file.

Compiler/Target/Microcontroller

TES-3243

TI TMS 320/C2000: Improved handling of special keywords for the CLANG parser.

*Enhancement***Compiler/Target/Microcontroller**

TES-3267

Es fehlt <token name="_Bool" value="TK_BOOL" output="_Bool"/>

Compiler/Target/Microcontroller

TES-3302

Fixed COMM-Makefiles. Generate Builtin Data failed in combination with support callback.

Compiler/Target/Microcontroller

TES-3335

Updated Wind River TriCore / Lauterbach TRACE32 Makefile template to support quotation marks within defines and removed wrenv dependency.

Enhancement

Release v4.2.8 (41 items)

Compiler/Target/Microcontroller

TES-3336

Fixed Renesas SuperH / Lauterbach TRACE32 COMM Makefile.

Compiler/Target/Microcontroller

Enhancement

TES-3341

Optimized handling of arrays within the TESSY-MATLAB interface.

Component Test

TES-3214

Fixed missing test evaluation of component tests when the "Apply to test result" preference option is set for a metric.

Defines

TES-3316

Fixed possible crash in defines parser when defines contain their name in the value (e.g. #define IO_ADDRESS IO_STRUCT.IO_ADDRESS)

Defines

TES-3346

Some define values were possibly not available if a source contains defines without a value.

Driver

Enhancement

TES-1857

Use Module stub code for unused external functions if available.

Driver

Enhancement

TES-3245

Sort compiler includes such that module includes are displayed first (and also used first when compiling the test driver code).

Driver

TES-3296

Fixed duplicate const at pointer to array parameter declaration.

Driver

TES-3350

Fixed generating initializer for enum class types.

Fault Injection

TES-3198

Fault injection could fail, if more than one source file was present in a module.

Instrumenter

TES-3351

Fixed instrumenting test object declared extern "C" inside C++ namespace.

Release v4.2.8 (41 items)

Interface Assigner (IDA)

TES-3332

Fixed possibly incorrect test data, user code and CTE tree after renaming a test object.

Interface Database (IDB)

TES-3276

If an advanced stub pointer targets a component inside a dynamic struct the value was lost after an interface change.

Interface Database (IDB)

TES-3325

Fixed erroneous display and driver of constructor with a function pointer parameter and following parameter.

Interface Editor (TIE)

TES-3329

Fixed initial passing for advanced stub variables that are pointers to incomplete structs.

Parser

TES-3199

Speed up the preparation of very large files with a huge number of empty lines for analysis.

Enhancement

Parser

TES-3291

Fixed parsing @ address directives for Cosmic compiler with legacy parser.

Parser

TES-3328

Fixed "asm volatile" problem in tks-windriver.tpl.

Plot View

TES-3287

Fixed potential exception in plot view when selecting modules, tasks, folders or test collections during the plot view update.

Report

TES-3314

Added optional TS/C metric into test details report.

Report

TES-3323

Fixed column width of statistics table within test details report.

Enhancement

Requirements

TES-3339

Various bugfixes for ReqIF import and export.

Release v4.2.8 (41 items)

Requirements

TES-3420

Fixed possible deadlock when creating/editing/deleting attributes for requirement and test case documents. Also fixed possible deadlock for ReqIF import using attributes.

Test Data Editor (TDE)

TES-3237

Fixed handling of erroneous inputs within "Show Array Elements" dialog.

Test Data Editor (TDE)

TES-3300

Fixed displaying test data of member variables of class reference parameter.

Test Data Editor (TDE)

TES-3312

Fixed creating dynamic object for triple *** pointer.

Variant Management

TES-3297

Fixed transferring call trace and prolog/epilog to variant module from test cases created with CTE in the base module.

Variant Management

TES-3298

Fixed synchronising test data from CTE. Inherited test data was possibly marked as overwritten.

Release v4.2.7 (43 items)

C++

TES-3202

The "this" object was sometimes not visible in test data editor TDE.

C++

TES-3239

Added new attributes 'Declare Constructors' and 'Deleted Constructors' to handle classes without or explicit deleted default constructor.

CTE

TES-3159

Fixed generating classification tree for bit field components.

CTE

TES-3217

From now modules can only be analyzed if all its CTE documents are saved. Moreover the CTE documents are closed automatically to force a reopen after module analysis.

Enhancement

Release v4.2.7 (43 items)

CTE

TES-3254

Now CTE document generation based on C++ sources is available.

New Feature

CTE

TES-3275

CTE_451 Now it's possible to change the text color.

CTE_54 Now the user can define font styles (type, weight, size) and text color for tree nodes and table entries.

CTE

TES-3277

Fixed updating of test data stemming from parsing CTE class node names with manually assigned test data for CTE tree nodes. All CTE-generated test data will be updated or deleted. Manually assigned test data for CTE class nodes that contain no parsable value will remain untouched.

CTE

TES-3284

Now the Test Data View will show generated test data without reselecting the CTE node.

Compiler/Target/Microcontroller

TES-3113

New combination for Wind River TriCore compiler with Lauterbach TRACE32 debugger.

New Feature

Compiler/Target/Microcontroller

TES-3170

Fixed idb-freescale-s12z.mk to support test object defines.

Compiler/Target/Microcontroller

TES-3178

Fixed idb-microchip-xc8.mak file. On some systems analyzing failed due to special preprocessor entries.

Compiler/Target/Microcontroller

TES-3179

Added support for the latest Green Hills V850 linker.

Compiler/Target/Microcontroller

TES-3183

Added support to TESSY's CLANG parser for `__int24` and `__uint24` data types for Microchip XC8 compiler.

Compiler/Target/Microcontroller

TES-3188

Fixed Makefile template for Cosmic S12Z in combination with winIDEA.

Compiler/Target/Microcontroller

TES-3189

Prepared GNU Tools for ARM+QEMU as well as all Crosscore Makefile template for parallel build.

Enhancement

Release v4.2.7 (43 items)

Compiler/Target/Microcontroller

TES-3196

Added Compiler Dialect variable to Microchip XC8-CC Makefile template.

Compiler/Target/Microcontroller

New Feature

TES-3201

Implemented support for multiple files in TEE attribute 'Duplicated Defines Header'.

Compiler/Target/Microcontroller

Enhancement

TES-3257

Added option -Xlicense-wait to all Wind River Makefile templates.

Compiler/Target/Microcontroller

Enhancement

TES-3259

Activated optional attribute "Wait Timeout" for GNU GCC/CDT test runs.

Component Test

TES-3182

Fixed component test driver for targets using file communication.

Driver

TES-3218

Fixed error when a pointer member inside a dynamic struct with passing OUT -> OUT is set to a dynamic object in one test case and set to NULL in a second test case.

Environment Editor (TEE)

TES-3169

Fixed TEE attributes with hex format flag.

Import/Export

TES-3211

Fixed errors in PTU import for array type variables.

Instrumenter

TES-3226

Instrumenter failed if a class member was defined "using namespace::class" but not directly inside the namespace.

Instrumenter

TES-3244

The instrumenter could crash if C++14 digit separators are used. [e.g. const double PI = 3.14159'26535'89793; const int MILLION = 1'000'000;]

Instrumenter

TES-3272

Instrumenter failed instrumenting static local variables when multiple variables are defined separated with comma and initialized using curly braces.

Release v4.2.7 (43 items)

Interface Assigner (IDA)

TES-3307

Fixed assignment of members in unassigned structs.

Interface Database (IDB)

TES-3197

Enum constants of enums without type name and tagname (enum {A, B, C};) used in test data had different values after automatic reuse.

Interface Database (IDB)

TES-3240

Consider change of bitfield size when comparing interface database.

Interface Database (IDB)

TES-3265

Possibly wrong associations between CTE tree elements and interface objects in test objects without test cases after module analysis.

Makefile Templates

TES-3208

Added support for defines using Atollic's GNU ARM compiler.

Enhancement

Parser

TES-3074

Updated all TKS template files and added a new TKS header for the AD compiler.

Parser

TES-3184

The parser could crash when trying to resolve header files from which static and inline functions should be excluded.

Parser

TES-3191

Fixed problem in ARMv6 TKS template file concerning volatile assembler functions.

Parser

TES-3241

Fixed possibly wrong typedef name for struct used in STL container template class.

Report

TES-3288

Fixed error when creating test details reports in non-PDF format for tasks with attachments.

Save/Restore Database (TMB Files)

TES-3210

Fixed possible removal of all CTE files during TMB import.

Release v4.2.7 (43 items)

Scenario Editor (SCE)

TES-3223

Fixed possible test data loss in scenario during time-consuming module analysis.

Scenario Editor (SCE)

TES-3232

When using the mode variable, it was possible to select static local variables. Also, for integer type variables it was not possible to assign a value.

TESSY (General)

TES-3204

Fixed skipping superfluous folder in module backup files saved with TESSY 4.2.5.

Test Database (TDB)

TES-3203

Fixed saving classification tree with pointers to nested unions.

Usercode Editor (UCE)

TES-2807

Apply attributes "Float Precision" and "Double Precision" to eval macros used in usercode.

Variant Management

TES-3238

Fixed purging obsolete comparison interface database to avoid annoying error message.

Release v4.2.6 (23 items)

C++

TES-3132

Fixed inserting stub code for a function following a struct template specialization.

C++

TES-3134

Fixed inserting stub code for static template method.

C++

TES-3153

Fixed generating parameter proxy class name for templates with reference or pointer template parameter.

C++

TES-3175

Fixed erroneous display of class reference parameter in TDE.

CTE

TES-3139

Fixed internal key collision error when using array parameters with "use as pointer".

Release v4.2.6 (23 items)

CTE

TES-3147

Fixed showing result at CTE Testcases in CTE perspective.

CTE

TES-3161

Fix that test data will not be generated automatically on CTE nodes for new pointer targets.

Command Line (tessycmd)

TES-3166

Fixed timestamp of problems.zlog file.

Command Line (tessycmd)

TES-3168

The TESSYD option --copy-log now creates the given directory if it does not exist.

Enhancement

Compiler/Target/Microcontroller

TES-3094

Reduced number of objects to be built and linked by default within TESSY's master Makefiles.

Enhancement

Compiler/Target/Microcontroller

TES-3155

IAR C-Spy: Settings folder was copied and right away deleted.

Driver

TES-3090

User defines were erroneously visible in slave control file.

Import/Export

TES-3135

Fixed creating synthetic structs and enums with typedef names on test data import.

Instrumenter

TES-3131

Fixed inserting user declarations to file with partly invalid preprocessor file information (in GNU syntax but with missing flag).

Interface Database (IDB)

TES-3158

Possible failure to rename large Interface Database folders when an antivirus software is running.

Metrics

TES-3137

Error enabling ET/AT metric or analyzing module when ET/AT metrics is enabled.

Report

TES-3146

Fixed series names of cyclomatic complexity (CC) metric graphics within overview report.

Release v4.2.6 (23 items)

TESSY (General)

TES-3141

Fixed restoring and importing TMB archives: A superfluous folder was created in TMB archives which caused the restore operation to fail.

TESSY (General)

TES-3157

Fixed potential timeout problem when starting processes.

TESSY hardware adapter interface (THAI)

TES-3142

Fixed evaluation of component tests when there are time steps that do not set signals within a scenario.

Test Database (TDB)

TES-3177

Fixed possible loss of generated test steps for generator test cases after automatic reuse operation.

Variant Management

TES-3140

Fixed wrong test data in variant test objects after synchronization if stub vector size has changed.

Variant Management

TES-3144

Fixed an exception during synchronization if a test object that is marked as removed is present.

Release v4.2.5 (94 items)

Application Notes

TES-2875

Updated TASKING VX application note.

C++

TES-2884

When a typedef of a struct declared inside a class is used in a template it's namespace was missing in the interface database.

C++

TES-2995

Class member variables were not evaluated when a class has a copy constructor or the tested method uses its own class as parameter. This could result in tests being shown as passed even though the member variables did not yield the expected result.

C++

TES-2998

Fixed possible error loading the interface database if a typedef inside a class uses a qualified type that is an inherited type of its base class.

Release v4.2.5 (94 items)

C++

TES-3009

Support references to scalar types in advanced stubs.

Enhancement

C++

TES-3013

In certain situations, an object used as a parameter for calling the test object can or must be created in the user code.

To be able to bind that object to the parameter used by TESSY for the test object call, for each parameter that is a reference to a structure or class with passing direction EXTERNAL, TESSY creates a template with the name "TESSY_BIND_PARAMETER_<name of parameter>", e.g. "TESSY_BIND_PARAMETER_foo_param".

This template can be used in the prolog to bind the user-generated object to the parameter. [e.g. MyClass & myVariable = MyFactory::createObject; TESSY_BIND_PARAMETER_myParameter(myVariable);]

Creating these templates will be enabled via the "Generate Parameter Proxies" attribute.

Enhancement

C++

TES-3035

Enabled setjmp/longjmp for C++ test objects.

C++

TES-3037

Pass direction of class members can now be set to EXTERN.

C++

TES-3060

For test objects, that are extern "C" contained in a namespace, TESSY failed to open the coverage flow file.

C++

TES-3098

If the attribute "Generate Parameter Proxies" is enabled an erroneous code was generated for template parameter.

C++

TES-3125

For test objects, that are extern "C" functions contained in a namespace, the stub code was missing.

C++

TES-3127

If a method definition, for that another method with the same name exists, is explicitly specified inline, the instrumenter failed to find the method.

CTE

TES-3051

Fix that the CTE shows an error when saving documents for C++ test objects.

Release v4.2.5 (94 items)**CTE****Enhancement**

TES-3057

CTE152 Now "Select All" (CTRL+A) selects all marks in the same test table column of the currently selected mark.

CTE457 Fixed that the CTE failed to open a refinement.

CTE477 Fixed typo in the layout preference page.

CTE465 Fixes an error with multiary dependency operators (AND, OR, XOR). Improves error messages when dependency inputs are missing.

CTE456 Fix that marks of refined nodes are sometimes shown as conflicting after all conflicts in the sub tree are solved.

CTE448 Fixed an issue where validation error markers at the top of the table moved downwards.

CTE450 Fixed that it was possible to copy and paste the table itself.

CTE476 Fixes that a group could be moved to itself or to an own subgroup.

CTE439 Now a test case is converted into a test step when dropping it into a test sequence.

CTE453 The synchronisation of the selected table entry sometimes stopped working.

CTE468 Fixes an error where already existing test cases are added again.

CTE460 Fixed that color is not removable with the red cross next to the color chooser.

CTE454 Fixed an error where opening refinements containing only one composition or classification failed.

CTE342 Now an automatic layout of the changed subtree is triggered when the layout mode was changed via properties view. This feature can be enabled/disabled via Preferences > CTE > Layout Settings

CTE381 Now very fast inserted tree nodes will always be placed side by side.

CTE469 Fixed message text in validation issues view for incomplete dependency operations (NOT, AND, OR, XOR).

CTE447 Optimized the insertion point of new children. Pasted nodes won't hide existing children of the current parent anymore.

CTE479 Fix that sometimes the CTE import of legacy '*.cte' files does not insert refinements in the tree structure.

CTE**Enhancement**

TES-3064

Now the automatic tree generation creates additional min value nodes for enums with min value > 0.

CTE

TES-3066

Fix that a potential stale CTE is not closed after an external change to a test object.

CTE

TES-3092

Don't try to generate a interface based classification tree for test objects from C++ projects which leads to errors. Currently this operation is only supported for C projects.

CTE

TES-3110

Fixed hidden CTE editor after resetting the CTE Perspective.

CTE

TES-3111

Optimized opening large CTEs.

Release v4.2.5 (94 items)

CTE

TES-3130

CTE484 Changed the default for preference "Pin original layout on import" to true.

CTE140 Optimized redraw of CTE while resizing the editor.

CTE488 Optimized time needed to close a CTE document.

CTE486 Newly created test table entries are visible and selected in all open editors of the same resource.

Enhancement

Command Line (tessycmd)

TES-3096

Fixed error reporting for CLI so that all errors/warnings appear within the problems log.

Command Line (tessycmd)

TES-3107

Create problems.zlog archive on exit to keep the errors/warnings from multiple subsequent TESSY sessions. Also added "--copy-log <directory>" option to TESSYD to allow copying the problems.zlog to the Jenkins workspace for archiving of artefacts in CLI operation mode.

Enhancement

Compiler/Target/Microcontroller

TES-2897

Added optional file communication for TRACE32 to speed up execution time on target hardware.

New Feature

Compiler/Target/Microcontroller

TES-2917

Fixed and updated Wind River makefile templates.

Compiler/Target/Microcontroller

TES-2929

New combination for GNU Tools for ARM with iSYSTEM winIDEA.

New Feature

Compiler/Target/Microcontroller

TES-2942

Added support for MATLAB TargetLink.

Enhancement

Compiler/Target/Microcontroller

TES-2944

New combination for Keil ARM compiler version 6 with SEGGER JLink.

Enhancement

Compiler/Target/Microcontroller

TES-2973

Fixed TEE attribute substitution and validation: It was possible that attributes (e.g. "Compiler Install Path") were substituted with attribut values of lower levels (e.g. "Target Install Path"). Also the error/warning icons were shown in some situations for inherited and not overwritten attributes.

Compiler/Target/Microcontroller

TES-2993

Fixed Boolean value in Renesas RX C++ type table.

Compiler/Target/Microcontroller

TES-3007

Fixed type table entries concerning _Bool.

Release v4.2.5 (94 items)

Compiler/Target/Microcontroller

TES-3016

Added missing compiler lds to tks-iar.tpl.

Compiler/Target/Microcontroller

TES-3023

Fixed tracing for gdb-file master.

Compiler/Target/Microcontroller

TES-3033

Microchip compiler XC8 was set to obsolete. Please use Microchip compiler XC8-CC instead or select "Show Obsolete Entries" from the TEE menu.

Enhancement

Compiler/Target/Microcontroller

TES-3071

Fixed race condition in multiple makefile templates, which occurred when attribute "Make Options" was set to compile in parallel, e.g. '-j 20', with multiple source files attached.

Component Test

TES-2980

Fixed possible loss of test data for dynamic objects if a pointer is removed from the interface.

Coverage Viewer (CV)

TES-2545

Generating the flow chart report failed if the 'Logo Image' path within the report preferences was not empty and did not contain an absolute path name.

Coverage Viewer (CV)

TES-3017

Fixed CPC coverage call position calculation (for display of source locations) for calls directly following a return statement.

Defines

TES-3062

Take "Float Precision" and/or "Double Precision" attribute into account when collecting define values.

Driver

TES-2992

Fixed erroneous struct declaration of typedef struct in old test driver when Enable User Includes is enabled.

Driver

TES-2999

Fixed possible communication error when resolving first union component as pointer target.

Driver

TES-3038

Fixed error generating parameter helper variable of a reference to a template with reference template parameter.

Release v4.2.5 (94 items)

Driver

TES-3043

Declare synthetic variables in all sources where the type is known.

Driver

TES-3084

Fixed generating #undef statements for static variable #define prior to all stub functions having a parameter with the same name as the static variable.

Driver

TES-3101

Fixed generating code for complex reference parameter when attribute 'Generate Constructors' is false.

Environment Editor (TEE)

TES-3055

Fixed using the internal environment variable TESSY_SOURCE_ROOT instead of SOURCEROOT when collapsing a file or directory path.

Import/Export

TES-3089

Restoring projects with C++ Test Objects and CTE documents fails if the test objects have long signatures.

Instrumenter

TES-2701

Added support for range based "for" loops [e.g. for (int i : array) { ... }].

Instrumenter

TES-2971

The instrumenter failed to match the destructor in a template class if not inlined. Due to that stub code written for the constructor was also inserted into the destructor.

Instrumenter

TES-2982

The instrumenter failed to stub methods inside a class that follows immediately after a function template.

Instrumenter

TES-2984

The instrumenter failed to find function definitions if a preprocessor line is present between name and parameter list.

Instrumenter

TES-3047

Allow wildcards in header file names within TEE attribute "Instrumenter Header Exclude List".

Instrumenter

TES-3053

The instrumenter failed to find function definitions if the return type is a pointer or reference to a qualified template, e.g.:

```
std::pair<int,int> & function_name (...  
std::pair<int,int> * function_name (...
```

Release v4.2.5 (94 items)

Instrumenter

TES-3119

Missing instrumentation if the initialization statement of a "for" loop ends with a function call. [e.g. for (int i = foo();...)]

Instrumenter

TES-3120

If call pair coverage (CPC) is enabled, the initialization expression for a local variable could be missing.

Interface Assigner (IDA)

TES-2983

Fixed automatic assignment of static global variables.

Interface Assigner (IDA)

TES-3027

Fix changed component names for pointer targeting the component in a dynamic struct,

Interface Assigner (IDA)

TES-3114

Test specification (CTE File) was deleted when renaming a test object.

Interface Database (IDB)

TES-2108

Fixed memory and performance problems when comparing large C++ interface databases.

Interface Database (IDB)

TES-2994

Possible missing stub code after auto reuse for external stub functions, if only the scope of that function has changed.

Interface Database (IDB)

TES-3010

Fixed possible loss of test data during comparison of interfaces with more than 500 functions when using the legacy parser.

Interface Database (IDB)

TES-3046

Allowing wildcards in header file names within the TEE attributes "Header File Exclude List" and "Header File Include List".

Enhancement

Interface Database (IDB)

TES-3082

OUT/EXTERN const variables were set to IRRELEVANT after importing TMB files from TESSY v4.0 or prior.

Interface Database (IDB)

TES-3085

Fixed performance problem when reusing interface databases with pointers.

Release v4.2.5 (94 items)

Interface Database (IDB)

TES-3099

Possibly erroneous test driver for const class member variables.

Interface Editor (TIE)

TES-3080

Fixed missing properties view contents for variables within TIE.

Interface Editor (TIE)

TES-3087

Allow pass direction EXTERN for const variables.

Enhancement

Metrics

TES-3103

Update the default formula for estimated time calculation.

Enhancement

Parser

TES-2922

Fixed parser error if ARMv5 builtins `__svc`, `__svc_indirect` or `__align` are used.

Parser

TES-2991

Parser failed to parse file if an initializer expression was neither int nor float.

Parser

TES-3030

Added `__int24`, `__uint24`, and `__at()` to Microchip TKS and header files.

Parser

TES-3091

Fixed storing source number of types when attribute 'Collect All Enums' is true.

Parser

TES-3095

Fixed parsing local static variables of test objects that were declared after a statement block.

Parser

TES-3171

Support usage of gcc option `-funsigned-char`.

Report

TES-2974

Overview report XML: Fixed percentage attribute value for called function coverage (without '%' now).

Report

TES-3004

Fix plots not being rendered in reports in Windows 10 versions newer than 1803.

Release v4.2.5 (94 items)

Report

TES-3380

Fixed potential deadlock problem when generating test details report that includes notes.

Requirements

TES-3003

Test case links could get lost in certain situations: Changes of test case links (adding, updating or deleting links) caused all not altered links of all test cases of the respective test object to be lost if TESSY was restarted. As a workaround, when executing such test objects after changing the links, the changes were persisted correctly and no links were lost.

Requirements

TES-3032

Fix display error in VxV matrix view when adjusting column width.

Save/Restore Database (TMB Files)

TES-2510

If a test object is removed, has interface changes, or does not have a valid interface, it will no longer be attempted to save a script file for it during database backup.

Save/Restore Database (TMB Files)

TES-2986

Allow canceling TESSY shutdown when backing up modules or if any jobs are still running.

Scenario Editor (SCE)

TES-3097

Added alphabetical sorting of functions within the component functions and called functions view.

Scenario Editor (SCE)

TES-3112

Fixed potential exceptions when switching to invalid scenarios or test objects with changed interface.

Script Editor

TES-2854

Committing script editor changes for component tests caused loss of dynamic objects under certain conditions.

Script Editor

TES-3034

Fixed problems when working with the script editor or importing/saving/restoring script files: Special characters within the time unit of component tests and stub functions with array indices within the signature caused problems.

TESSY (General)

TES-2990

Enhanced DOXYGEN comment handling: In case of errors while parsing the DOXYGEN output, existing specification entries will be voided. Comments inside the function will not be collected by default.

Enhancement

Release v4.2.5 (94 items)

TESSY (General)

Enhancement

TES-3014

All source and header files that are shown in the TESSY Message Console are now displayed as hyperlinks and can be opened with a double-click in the C/C++ perspective.

TESSY (General)

TES-3108

Fixed potential race condition when starting TESSY which caused the derby daemon to be terminated.

Test Data Editor (TDE)

TES-3011

Fixed missing child elements for pointer and reference objects in the usercode proposal list.

Test Data Editor (TDE)

TES-3012

Fixed wrong entries in the usercode proposal list for "THIS" if the object class is located inside a namespace.

Test Database (TDB)

TES-3028

The unexpected shutdown of the DBD process after module analysis was fixed. This error occurred if no test objects were available after the analysis due to a filter, but they were available after the filter was corrected.

Variant Management

TES-2981

If an expression is used as expected value for an interface object with passing direction INOUT, this value was set to null during test data verification in variant test objects.

Variant Management

TES-2997

Disable "Create Pointer Target Value" for test objects in variant modules (regardless whether inherited or not).

Variant Management

TES-3018

Define values in the test data of variants created with a TESSY version prior to 4.1 were marked as invalid after module synchronization.

Variant Management

TES-3026

For pointers with passing direction OUT pointing into a dynamic object with passing direction IN, these pointers were marked as failed during test evaluation.

Release v4.2.4 (19 items)

CTE

New Feature

TES-2517

A generator for classification trees has been added that generates a new tree based on the interface of a test object. A classification will be generated for each input variable with the possible values as classes according to the equivalence partitioning method.

Release v4.2.4 (19 items)

CTE

TES-2576

Improved version of pair-wise test case generation.

Enhancement

CTE

TES-2610

The new project-wide data dictionary provides means to assign application domain related names to implementation variables that can be used throughout all CTE test specifications. Data dictionary entries will be synchronized on interface changes and related CTE classifications will be updated automatically.

New Feature

Compiler/Target/Microcontroller

TES-2667

IAR C-SPY simulator test runs are executed in parallel now which reduces overall execution time.

Enhancement

Compiler/Target/Microcontroller

TES-2716

New combination for GNU Toolchain for PowerPC in conjunction with PLS UDE.

New Feature

Component Test

TES-1255

Fixed problems with test driver generation when multiple source files were used.

Enhancement

Component Test

TES-2002

The component test feature is now also available for C++ modules.

New Feature

Coverage Measurement

TES-2559

The new call pair coverage measurement (CPC) now supports measuring if all call locations of functions or methods within the test object have been exercised at least once. This fulfills the requirements of ISO 26262 as an alternate coverage method for integration testing instead of applying the function coverage (FC) method.

New Feature

Fault Injection

TES-1863

Added option to automatically leave code loops after the first loop iteration using fault injections.

New Feature

License Manager

TES-1517

Enable and disable license server usage statistic logging by flsutil.

Enhancement

Metrics

TES-2792

Added "Test Step To Complexity Ratio" metric.

New Feature

Requirements

TES-840

The requirement document preview is now available for all TESSY perspectives. The desired document to display can be selected within the view.

Enhancement

Release v4.2.4 (19 items)

Requirements

New Feature

TES-1468

A new task element provides means to protocol external tests and reviews and link them to requirements. This allows full verification coverage of requirements that are not testable with a normal unit or integration test.

Requirements

Enhancement

TES-2913

The default test means "Unit" and "Component" will now only be created on startup of TESSY if there are no other test means defined (e.g. if the default ones have been renamed).

Save/Restore Database (TMB Files)

Enhancement

TES-2624

New option "Use default coverage selection for all modules" added to coverage preference page in order to overwrite coverage selections stored within TMB files being imported.

TESSY (General)

Enhancement

TES-2035

Completely reworked error handling to provide enhanced error messages and logging capabilities for command line execution. New error dialog shows the full exception chain, the context (e.g. the affected test object) and provides easy access to the error log file.

TESSY (General)

New Feature

TES-2117

The new testing effort estimation is based on a customizable formula that is based on the available metrics provided by TESSY. Additional metrics have been added that can also be used within the time estimation formula:

- Number of statements
- Number of calls
- Nesting depth

When analyzing a module, the estimated time is updated based on the given formula. The actual time can be tracked within the test project view for each test object.

TESSY (General)

Enhancement

TES-2586

Enhanced handling and feedback when configuring the TESSY floating license manager.

Test Execution

Enhancement

TES-2715

Added option to automatically retry execution for aborted test objects.