

Linux installation

Technical requirements

TESSY is available for Linux platforms starting with Ubuntu 20.04 since TESSY 5.0. Legacy versions will not be supported.

The TESSY Linux version supports the GNU/GCC compiler and Eclipse debugger as target environment. Further compiler and target environments that are available on Linux will be supported on demand.

To operate TESSY you need to install both TESSY and the Floating License Server (FLS) as described below.

Table of Contents

1. Setup	2
Ubuntu 20.04 LTS (Focal Fossa)	2
Ubuntu 22.04 LTS (Jammy Jellyfish)	2
2. Installation.....	2
3. Registration.....	3

1. Setup

To install TESSY on a Debian based Linux distribution you need to add a trusted repository first. This only needs to be done once. To add a trusted repository you have to open a shell window and execute the following commands:

```
$ sudo -i
```

Install the Razorcat public key such that your Ubuntu system can verify the package downloads:

```
# wget -O - http://www.razorcat.com/deb/razorcat-signing-key.asc \  
| gpg --dearmor - | tee /etc/apt/trusted.gpg.d/razorcat.gpg >/dev/null
```

Now you have to add an APT repository according to your Ubuntu version. If you are unsure about your Ubuntu version use the following to show the version.

```
# lsb_release -a
```

Ubuntu 20.04 LTS (Focal Fossa)

Execute this on a system running Ubuntu 20.04:

```
# echo 'deb [arch=amd64] http://www.razorcat.com/deb/ focal contrib' \  
>>/etc/apt/sources.list.d/razorcat.list
```

Ubuntu 22.04 LTS (Jammy Jellyfish)

Execute this on a system running Ubuntu 22.04:

```
# echo 'deb [arch=amd64] http://www.razorcat.com/deb/ jammy contrib' \  
>>/etc/apt/sources.list.d/razorcat.list
```

2. Installation

Installing the current version of TESSY/FLS within the root shell:

```
# apt-get update  
# apt-get install rc-tessy-5.0 -y  
# apt-get install rc-fls -y
```

Installing a specific version of TESSY/FLS within the root shell:

```
# apt-cache policy rc-tessy-5.0
```

This will show the available versions, e.g.:

```
rc-tessy-5.0:
Installed: 5.0.1-1+123.1:
Candidate: 5.0.2-1+28.1
Version table:
5.0.2-1+28.1 500
500 http://www.razorcat.com/deb focal/contrib amd64 Packages
*** 5.0.1-1+123.1 500
500 http://www.razorcat.com/deb focal/contrib amd64 Packages
100 /var/lib/dpkg/status
5.0.1-1+108.4 500
500 http://www.razorcat.com/deb focal/contrib amd64 Packages
5.0.1-1+108.3 500
500 http://www.razorcat.com/deb focal/contrib amd64 Packages
```

Installing a selected version, e.g.:

```
# apt-get install rc-tessy-5.0=5.0.2-1+28.1
```

3. Registration

A license request should be executed in a shell as a normal user (not as root user).
Requesting a license:

```
$ /opt/razorcat/fls/bin/flsutil request-license
```

This will open the license request web page on the Razorcat website.

If you requested the license within the root shell by mistake, you will see a message similar to this:

```
Please, open the following URL:
https://www.razorcat.com/en/tessy_key_request.html?hostid=46AD17017AAF-000-07
```

In this case please copy the displayed URL and open it manually using a web browser.
This will also lead to the license request web page on the Razorcat website.

Fill in and submit the license request form on the web page and you will receive a license file from our support team. Copy this license file to your local disk.

Installing the license to a proper location and starting the license server:

```
# /opt/razorcat/fls/bin/flsutil install-license license.txt
# systemctl enable rc-fls
Created symlink /etc/systemd/system/multi-user.target.wants/rc-fls.service
/lib/systemd/system/rc-fls.service.
# systemctl start rc-fls
```

Checking for problems with the license server:



TESSY Application Notes

```
# /opt/razorcat/fls/bin/flsd --foreground -verbose
```

This will start the license server as an application and put out diagnostic messages.

In case of any problems please contact support@razorcat.com.